

LibraryLibLidarLms151

Generated by Doxygen 1.8.6

Mon Feb 1 2016 14:24:44

Contents

1	File Index	1
1.1	File List	1
2	File Documentation	3
2.1	Library_LibLidarLms151.c File Reference	3
2.1.1	Detailed Description	4
2.1.2	Macro Definition Documentation	4
2.1.2.1	K_BUFFER_SIZE_MAX	4
2.1.3	Enumeration Type Documentation	4
2.1.3.1	te_ContentOutChannel	4
2.1.3.2	te_ReadStatus	5
2.1.3.3	te_subState	5
2.1.4	Function Documentation	5
2.1.4.1	LibLidarLms151_Close	5
2.1.4.2	LibLidarLms151_Configure	5
2.1.4.3	LibLidarLms151_Get_InternalState	5
2.1.4.4	LibLidarLms151_Get_Mode	6
2.1.4.5	LibLidarLms151_Get_Scan	6
2.1.4.6	LibLidarLms151_Get_Status	6
2.1.4.7	LibLidarLms151_Get_Timestamp	7
2.1.4.8	LibLidarLms151_Initialize	7
2.1.4.9	LibLidarLms151_Manage	7
2.1.4.10	LibLidarLms151_Open	9
	Index	11

Chapter 1

File Index

1.1 File List

Here is a list of all documented files with brief descriptions:

Library_LibLidarLms151.c	
Fichier Source du Service LibLidarLms151	3

Chapter 2


File Documentation

2.1 Library_LibLidarLms151.c File Reference

Fichier Source du Service LibLidarLms151.

```
#include "types.h"
#include "Library_StdLib.h"
#include "Library_LibLidarLms151.h"
#include "Driver_TcpSocketDriver.h"
#include <string.h>
#include <stdlib.h>
#include <stdio.h>
#include <errno.h>
```

Include dependency graph for Library_LibLidarLms151.c:



Macros

- #define **K_BUFFER_SIZE_MAX** 262144ul /*! buffer maximal size value */
- #define **K_START** 1 /*! Start value */
- #define **K_AMOUNT_OF_ENCODERS_MAX** 3 /*! Maximum amount of encoders */
- #define **K_AMOUNT_OF_16BITS_CHANNELS_MAX** 2 /*! Maximum amount of 16bits channels */
- #define **K_AMOUNT_OF_8BITS_CHANNELS_MAX** 2 /*! Maximum amount of 8bits channels */

Enumerations

- enum **te_command_status** { **E_COMMAND_ERROR** =0, **E_COMMAND_SUCCESS** }
define the command status
- enum **te_start_status** { **E_START_NO_ERROR** =0, **E_START_NOT_ALLOWED** }
define the start status
- enum **te_subState** { **E_IDLE** = 0, **E_READ**, **E_ERROR** }
define the mode substate
- enum **te_ReadStatus** { **E_READ_BUSY** =0, **E_READ_FINISH**, **E_READ_NO_DATA** }

define the read status

- enum [te_ContentOutChannel](#) { [E_OUT_DIST1](#) = 0, [E_OUT_DIST2](#), [E_OUT_RSSI1](#), [E_OUT_RSSI2](#) }

define the lidar Content Out channel

Functions

- Std_ReturnType [LibLidarLms151_Initialize](#) (void)
this function initialize module
- Std_ReturnType [LibLidarLms151_Configure](#) (const ts_LibLidarLms151_Configuration *const ps_LibLidarLms151_Configuration)
- Std_ReturnType [LibLidarLms151_Manage](#) (void)
this function is the central point of the library, it manage the laser
- Std_ReturnType [LibLidarLms151_Open](#) (void)
this function will open Tcp Socket needed for communication with Lms151
- Std_ReturnType [LibLidarLms151_Close](#) (void)
this function will close Tcp Socket needed for communication with Lms151
- Std_ReturnType [LibLidarLms151_Get_Timestamp](#) (uint32 *const pu32_Timestamp)
this function will return Laser data Timestamp
- Std_ReturnType [LibLidarLms151_Get_Scan](#) (ts_LibLidarLms151_scan_data *const ps_LibLidarLms151_scan_data)
this function will return scan values
- Std_ReturnType [LibLidarLms151_Get_InternalState](#) (te_InternalStateMachine *const pe_State)
this function will return internal state
- Std_ReturnType [LibLidarLms151_Get_Status](#) (te_LibLidarLms151_device_status *const pe_LibLidarLms151_device_status)
this function will return laser status
- Std_ReturnType [LibLidarLms151_Get_Mode](#) (te_mode *const pe_Mode)
this function will return global mode

2.1.1 Detailed Description

Fichier Source du Service LibLidarLms151. \$Source: [Library_LibLidarLms151.c](#) \$Author: Slo \$Date: 2016/01/14

2.1.2 Macro Definition Documentation

2.1.2.1 #define K_BUFFER_SIZE_MAX 262144ul /*! buffer maximal size value */

Global constant Reserved value "1"

2.1.3 Enumeration Type Documentation

2.1.3.1 enum te_ContentOutChannel

define the lidar Content Out channel

Enumerator

- [E_OUT_DIST2](#)** Content channel is DIST1
- [E_OUT_RSSI1](#)** Content channel is DIST2
- [E_OUT_RSSI2](#)** Content channel is RSSI1
Content channel is RSSI2

2.1.3.2 enum te_ReadStatus

define the read status

Enumerator

E_READ_FINISH Read busy
E_READ_NO_DATA Read finished
 No data read

2.1.3.3 enum te_subState

define the mode substate

Enumerator

E_READ Mode is in IDLE state
E_ERROR Mode is actually in Read state
 Mode is in Error state

2.1.4 Function Documentation

2.1.4.1 Std_ReturnType LibLidarLms151_Close (void)

this function will close Tcp Socket needed for communication with Lms151

Parameters

<i>none</i>	
-------------	--

Returns

Std_ReturnType :

- E_NOT_OK if module is not initialized or Tcp socket return an error
- else E_OK

Tcp Socket Close Error, t_Close_Status is set to E_NOT_OK

no Tcp Socket Close Error, t_Close_Status is set to E_OK

Module is not initialized, Halt

2.1.4.2 Std_ReturnType LibLidarLms151_Configure (const ts_LibLidarLms151_Configuration *const ps_LibLidarLms151_Configuration)

Set Laser configuration

Set data configuration

Set socket configuration

Module is not initialized, Halt

2.1.4.3 Std_ReturnType LibLidarLms151_Get_InternalState (te_InternalStateMachine *const pe_State)

this function will return internal state

Parameters

<i>te_InternalState-Machine</i>	*pe_State : state parameter
---------------------------------	-----------------------------

Returns

Std_ReturnType :

- E_NOT_OK if pe_State is null or module is not initialized
- else E_OK

Module is not initialized, Halt

2.1.4.4 Std_ReturnType LibLidarLms151_Get_Mode (te_mode *const pe_Mode)

this function will return global mode

Parameters

<i>te_mode</i>	*pe_Mode : mode parameter
----------------	---------------------------

Returns

Std_ReturnType :

- E_NOT_OK if pe_Mode is null or module is not initialized
- else E_OK

Module is not initialized, Halt

2.1.4.5 Std_ReturnType LibLidarLms151_Get_Scan (ts_LibLidarLms151_scan_data *const ps_LibLidarLms151_scan_data)

this function will return scan values

Parameters

<i>ts_LibLidar-Lms151_scan-data</i>	*ps_LibLidarLms151_scan_data : scan parameter
-------------------------------------	---

Returns

Std_ReturnType :

- E_NOT_OK if ps_LibLidarLms151_scan_data is null or module is not initialized
- else E_OK

Module is not initialized, Halt

2.1.4.6 Std_ReturnType LibLidarLms151_Get_Status (te_LibLidarLms151_device_status *const pe_LibLidarLms151_device_status)

this function will return laser status

Parameters

<i>te_LibLidarLms151_device_status</i>	*pe_LibLidarLms151_device_status : device status parameter
--	--

Returns

Std_ReturnType :

- E_NOT_OK if pe_LibLidarLms151_device_status is null or module is not initialized
- else E_OK

Module is not initialized, Halt

2.1.4.7 Std_ReturnType LibLidarLms151_Get_Timestamp (uint32 *const pu32_Timestamp)

this function will return Laser data Timestamp

Parameters

<i>uint32</i>	*pu32_Timestamp : timestamp parameter
---------------	---------------------------------------

Returns

Std_ReturnType :

- E_NOT_OK if pu32_Timestamp is null or module is not initialized
- else E_OK

Module is not initialized, Halt

2.1.4.8 Std_ReturnType LibLidarLms151_Initialize (void)

this function initialize module

Parameters

<i>none</i>	
-------------	--

Returns

Std_ReturnType :

- E_OK if SrvConf_Get_Lms151TcpSocket, LibLidarLms151_Open and SrvConf_Get_Lms151Output-Mode return functions are E_OK
- E_NOT_OK if not

2.1.4.9 Std_ReturnType LibLidarLms151_Manage (void)

this function is the central point of the library, it manage the laser

Parameters

<i>none</i>	
-------------	--

Returns

Std_ReturnType :

- E_OK if good return function
- E_NOT_OK if not

Check Module is Initialized and configured

Module Initialized, it has to be configured

set ge_InternalStateMachine to E_LIBLMS151_STATUS_CONFIGURATION

set ge_Mode to E_MODE_LOGIN

set ge_SubState to E_IDLE

log into laser for parameters modifications

Check login command has been well sent

if check is ok, set ge_mode to E_MODE_SET_FREQUENCY_AND_RESOLUTION and ge_SubState to E_IDLE

Configure laser Frequency and resolution

Check laser frequency and resolution configuration well done

if check is ok, set ge_mode to E_MODE_CONFIGURE_SCAN_DATA_CONTENT and ge_SubState to E_IDLE

Configure scan data content

Check scan data content configuration has been well done

if check is ok, set ge_mode to E_MODE_CONFIGURE_SCAN_DATA_OUTPUT and ge_SubState to E_IDLE

configure laser scan data output

check scan data output laser command has been well sent

if check is ok, set ge_mode to E_MODE_STORE_PARAMETERS and ge_SubState to E_IDLE

Store parameters in laser eeprom

if check is ok, set ge_mode to E_MODE_START_MEAS and ge_SubState to E_IDLE

Start Measurements

Check start measurements command has been well sent

if check is ok, set ge_mode to E_MODE_ASK_STATUS and ge_SubState to E_IDLE and ge_InternalStateMachine to E_READY

Ask laser state

Check laser ask state command has been well sent

if check is ok, set ge_mode to E_MODE_LOGOUT and ge_SubState to E_IDLE

log out to run laser

Check log out command has been well sent

if check is ok, set ge_mode to E_MODE_SCAN_CONTINUOUS and ge_SubState to E_IDLE and ge_InternalStateMachine to E_STATE_SCAN

Configure permanent scan

if check is ok, set ge_mode to E_MODE_GET_DATA and ge_SubState to E_IDLE and gu32_FramePosition to 0

Receive data from laser

Module is not initialized, Halt

2.1.4.10 Std_ReturnType LibLidarLms151_Open (void)

this function will open Tcp Socket needed for communication with Lms151

Parameters

<i>none</i>	
-------------	--

Returns

Std_ReturnType :

- E_NOT_OK if module is not initialized or Tcp socket return an error
- else E_OK

Tcp Socket Open Error, t_Open_Status is set to E_NOT_OK

no Tcp Socket Open Error, t_Open_Status is set to E_OK

Module is not initialized, Halt

Index

E_ERROR
Library_LibLidarLms151.c, [5](#)

E_OUT_DIST2
Library_LibLidarLms151.c, [4](#)

E_OUT_RSSI1
Library_LibLidarLms151.c, [4](#)

E_OUT_RSSI2
Library_LibLidarLms151.c, [4](#)

E_READ
Library_LibLidarLms151.c, [5](#)

E_READ_FINISH
Library_LibLidarLms151.c, [5](#)

E_READ_NO_DATA
Library_LibLidarLms151.c, [5](#)

LibLidarLms151_Close
Library_LibLidarLms151.c, [5](#)

LibLidarLms151_Configure
Library_LibLidarLms151.c, [5](#)

LibLidarLms151_Get_InternalState
Library_LibLidarLms151.c, [5](#)

LibLidarLms151_Get_Mode
Library_LibLidarLms151.c, [6](#)

LibLidarLms151_Get_Scan
Library_LibLidarLms151.c, [6](#)

LibLidarLms151_Get_Status
Library_LibLidarLms151.c, [6](#)

LibLidarLms151_Get_Timestamp
Library_LibLidarLms151.c, [7](#)

LibLidarLms151_Initialize
Library_LibLidarLms151.c, [7](#)

LibLidarLms151_Manage
Library_LibLidarLms151.c, [7](#)

LibLidarLms151_Open
Library_LibLidarLms151.c, [8](#)

Library_LibLidarLms151.c
E_ERROR, [5](#)
E_OUT_DIST2, [4](#)
E_OUT_RSSI1, [4](#)
E_OUT_RSSI2, [4](#)
E_READ, [5](#)
E_READ_FINISH, [5](#)
E_READ_NO_DATA, [5](#)

Library_LibLidarLms151.c, [3](#)
LibLidarLms151_Close, [5](#)
LibLidarLms151_Configure, [5](#)
LibLidarLms151_Get_InternalState, [5](#)
LibLidarLms151_Get_Mode, [6](#)
LibLidarLms151_Get_Scan, [6](#)
LibLidarLms151_Get_Status, [6](#)
LibLidarLms151_Get_Timestamp, [7](#)
LibLidarLms151_Initialize, [7](#)
LibLidarLms151_Manage, [7](#)
LibLidarLms151_Open, [8](#)
te_ContentOutChannel, [4](#)
te_ReadStatus, [4](#)
te_subState, [5](#)

te_ContentOutChannel
Library_LibLidarLms151.c, [4](#)

te_ReadStatus
Library_LibLidarLms151.c, [4](#)

te_subState
Library_LibLidarLms151.c, [5](#)